# combine\_spx

This code appends the data on one SPX file to another SPX file. This can be used to combine results when doing 'RESTART\_2' runs. That is, one folder has the results from 0 to 5 seconds. Another folder has the results from a 'restart\_2' for the next 5 seconds. This program will append the second folder results to the file in the first folder to allow for analysis of the entire data set.

### **Build Instructions**

### To build using g++

```
g++ combine spx.cpp MfixData.cpp -o cobine spx.exe
```

## **Usage**

### Notes:

- The first file is modified, consider backing it up before running the program
- The second file is left unchanged
- It is easiest if the two runs are in different folders
- Sample program execution

```
combine_spx.exe
note : this code does endian byte-swaps
enter first run name (without the .RES) (case sensititive) > a/BUB02
enter second run name (without the .RES) (case sensititive) > b/BUB02
enter the SPX file to combine (1-9) > 1
add last time of first file to each time in second file ? (0 = no) > 1
last time (first file) = 1.00135
a/BUB02.SP1
b/BUB02.SP1
```

processing time = 1.01183 = 1.00135 + 0.0104844

processing time = 1.02319 = 1.00135 + 0.0218424

processing time = 1.03193 = 1.00135 + 0.0305794

processing time = 1.04163 = 1.00135 + 0.0402871

processing time = 1.05134 = 1.00135 + 0.0499949

processing time = 1.06213 = 1.00135 + 0.0607813

.

.

.

processing time =	1.9526 =	1.00135 + 0.951252
processing time =	1.96458 =	1.00135 + 0.963236
processing time =	1.97302 =	1.00135 + 0.97167
processing time =	1.98189 =	1.00135 + 0.980548
processing time =	1.99521 =	1.00135 + 0.993864
processing time =	2.00507 =	1.00135 + 1.00373
updating record 3 value		